


How Do I Reset the Admin Password?


Harley Britcher - 2025-01-10 - Comments (0) - Lاسernet FAQs

In some cases, the Lاسernet administrator password may need to be reset. In order to do this, you will need admin rights on the server on which your Lاسernet Config Server is installed. To reset your password, perform the following actions:


1. Open the Windows **Start** menu and search for "services.msc".



2. Scroll down the services list to find the Lاسernet Config and Lاسernet 10 services.
3. Right-click each of them and click **Stop**.



- Open Task Manager and navigate to the details tab to locate any instances of **sqlservr.exe**.
- Right-click it and then click **End task**.



- Run a Windows Command Prompt with Admin permissions.
- Type `cd C:\Program Files\Formpipe Software\Lasetnet 10\` in order to change the directory to the Lasetnet 10 installations folder.
- Run LnConfig.exe in the Command Prompt with the following parameter:
LnConfig.exe -reset-admin-password.

Note

This will generate a list of database errors, as the database is no longer being utilized by the sqlservr.exe process. This means it is now open to a password reset. As a result, a new password for the admin account is generated and shown in the console. This must be changed when you next log into the config server website.

- In services.msc, restart the Lasetnet Config 10 and Lasetnet 10 Services.

The **sqlservr.exe** will automatically restart when the Lasetnet Config 10 and Lasetnet 10

Services are started.