

## How can I put Autoform DM in/out of DEBUG logging mode?

Alex Clemons - 2022-08-04 - Comments (0) - Autoform DM FAQs


# Autoform DM

This article is applicable only to standalone setups.

To put Autoform DM in or out of logging mode, change the **node.properties** file. To do this, follow these steps:

1. Open the **node.properties** file in the following location:

**OS(C:) > Program Files > Formpipe Software > Autoform DM > Server xx > wildfly xx > standalone > configuration > node.properties.**



Name	Date modified	Type	Size
standalone_xml_history	29/03/2022 11:56	File folder	
application-roles.properties	03/03/2022 16:22	Properties Source File	1 KB
application-users.properties	03/03/2022 16:22	Properties Source File	1 KB
dmserver.cer	03/03/2022 16:24	Security Certificate	1 KB
https.keystore	03/03/2022 16:24	KEYSTORE File	3 KB
logging.properties	29/03/2022 11:56	Properties Source File	9 KB
mgmt-groups.properties	03/03/2022 16:24	Properties Source File	1 KB
mgmt-users.properties	03/03/2022 16:24	Properties Source File	2 KB
<b>node.properties</b>	03/03/2022 16:57	Properties Source File	6 KB
standalone.xml	29/03/2022 11:45	XML Source File	40 KB
standalone-full.xml	03/03/2022 16:22	XML Source File	34 KB
standalone-full-ha.xml	03/03/2022 16:22	XML Source File	38 KB
standalone-ha.xml	03/03/2022 16:22	XML Source File	34 KB
standalone-load-balancer.xml	03/03/2022 16:22	XML Source File	7 KB
standalone-microprofile.xml	03/03/2022 16:22	XML Source File	23 KB
standalone-microprofile-ha.xml	03/03/2022 16:22	XML Source File	26 KB

2. Locate the lines shown below (see labels) and remove the **#** so property is read:

CODE

```
# Core Autoform DM code
```

```
#logging.level.efstech=INFO
```

```
# Web Services v1
```

```
#logging.level.apsuk=DEBUG
```

```
# Web Services v2
```

```
#logging.level.websvc21=DEBUG
```

```
# Connection pool logging
```

```
#logging.level.efstech.jca=DEBUG
```

3. Click **Save** and then restart Autoform DM to apply the changes.